

EZdok CAMERA ADDON For Microsoft Flight Simulator X

USER MANUAL

Ver. 1.15.1

CONTENTS

1. Introduction	3
2. Features	4
3. Note for advanced users	5
4. System requirements	6
5. Installation notes	7
6. Preliminary settings	8
7. Interface	10
8. Camera shaking modes	13
9. View modes control	14
10. Addon status indicator	15
11. General settings	16
12. TrackIR settings	18
13. Getting started	19
14. Switching between the cameras	21
15. Assigning keyboard shortcuts and joystick buttons for camera switching.	22
16. Creating, deleting and renaming Virtual Cockpit and Aircraft cameras.	24
17. Creating, deleting and renaming World cameras	25
18. Positioning cameras	26
19. Camera position limiter	27
20. Camera export and import	28
21. View modes settings	29
22. Camera Shake effects setting	
22.1 Brief description of RANDOM EFFECT settings	30
22.2 Brief description of DHM effect settings	34
22.3 Brief description of CAMERA RESONANCE effect settings	35
19. Video examples on youtube.com	36

1. INTRODUCTION

Ezdok Camera Addon (EZCA) greatly enhances view control in Flight Simulator X. It allows the user to travel within the virtual cockpit of the aircraft, around the aircraft, and around the Flight Simulator X world. The addon also simulates the visual effects of the pilot's head movements caused by vibration, turbulence, aircraft accelerations, and surface roughness when on the ground.

With EZCA you can place internal or external cameras “on-the-fly”, adjust its position, and turn on or off the appropriate camera shake effects. You can travel around the virtual cockpit and outside the aircraft using the mouse and keyboard like you do in 3D shooters. With the benefits of “Point-to-point” and “3D-panoraming” technologies you can make view control in FSX as nearly as convenient as with advanced hardware view control systems like Track-IR.

We hope developers of scenery addons for FSX will also find EZCA as a valuable tool. EZCA's ability of walking around the Flight Simulator world will help them to observe their objects from any point of view within Flight Simulator, helping them to avoid flaws and mistakes.

EZCA expands the possibilities of Flight Simulator X movie making and will be useful for addon developers as a tool that can improve the quality of promo videos of their products, as well as for movie making enthusiasts to get the most realistic effects and viewpoints.

Examples of videos made with EZCA

[Video1](#)

[Video2](#)

[Video3](#)

[Video4](#)

EZCA is created by Ezdok Software, and published in partnership with Flight One Software. Support is provided by Ezdok Software and Flight One Software staff via a customer support forum. We highly recommend you visit the forum and participate in discussions regarding EZCA to learn about features, to help offer suggestions, and to help make EZCA even more ground breaking.

To visit Ezdok Software: <http://www.ezdok-software.com>

To visit Flight One Software: <http://www.flight1.com>

For the EZCA discussion forum: <http://www.simforums.com/forums>

2. FEATURES

With EZCA you can:

- Travel throughout virtual cockpit or cabin of the aircraft, around the outside of the aircraft, and around the flight simulator world.
- Smoothly switch between the cameras (PtP technology). In this mode, the camera smoothly “floats” from the current position to a new position.
- Create up to 255 internal, external aircraft, and world cameras for every aircraft. Edit POV and locations of the camera “on-the-fly” with the mouse and keyboard.
- Switch between the cameras with joystick buttons or keyboard shortcuts.
- Enable and disable mouse look mode with the middle mouse button.
- Use 3D “panoraming” mode.
- Create and modify your own camera shake effects with the built-in effects editor.
- Import and export settings to an external files for back-up or sharing with other EZCA users. You can export camera settings and other settings for every single effect or module separately.

3. NOTE FOR ADVANCED USERS

Advanced users can create custom camera shake effects. This will require that the user has a clear comprehension of the EZCA operation principles. Creation of effects is described in separate document: Advanced Effects Manual.

4. SYSTEM REQUIREMENTS

1. Windows XP/Vista/7 32-bit or 64-bit.
2. Microsoft Flight Simulator X with SP1, SP2, or Acceleration Pack installed. The EZCA will not work on any simulator prior to FSX.
3. Hardware capable to maintain over 10 FPS in Flight Simulator X. For comfortable flying with camera shake effects on, we recommend that you fine tune the graphics settings of your Flight Simulator so that it can perform at more than 20 FPS.
4. Mouse with scroll wheel and middle button recommended.
5. TrackIR recommended.

5. INSTALLATION NOTES

If you use WINDOWS VISTA or WINDOWS 7, there are some specifics you may need to be aware of.

Because FSX by default is in the user-restricted Program Files folder, and camera entries need to be written to FSX, you need to make sure that User Account Control or other user settings in Vista or Windows 7 do not prevent the writing of data to the FSX folders. This may mean you need to turn User Account Control off, and/or right click the EZCA Config tool and select Run as Administrator. If you installed FSX outside of Program Files, the above may not apply.


6. PRELIMINARY SETTINGS

After you have successfully installed EZCA, you have to make some preparations.

1. In the FSX controllers setup menu disable the HAT-switch of the game controller you plan to use for view control, otherwise the assignments in FSX will interfere with EZCA and you will get erratic movement of the direction of sight. On the FSX **Options** menu click **Settings**, then **Controls**. Click **Button / Keys** and select the game controller of your choice from the list. Click **Views** on the **Event category** menu and delete Game controllers assignments from all the items that contain “pan”. For instance, **Look left (pan)**, **Look right (pan)**, etc.
2. Delete keyboard shortcut assignments **A**, **S**, **SHIFT-A**, **SHIFT-S**.
3. Remove keyboard assignments from arrow keys and keys 0, 1, 2, and 3 on the numeric keypad following the same principle.



4. Start the **EZCA Configurator** by clicking its icon on the desktop or choosing it from the **Programs** menu.
5. Click **START** and wait while the Configurator modifies the aircraft.cfg files of all the models installed in FSX. The Configurator doesn't make any significant changes to the aircraft.cfg files, it just adds a new “EZDOK universal camera” section.
6. When Configurator finishes his job, a list of successfully patched aircraft appears in the Configurator window. Click **OK**, then close Configurator. You will need to do this operation after installation of every new aircraft to FSX.




Note: If you want to uninstall EZCA, first start **Configurator** once again and click the **Restore** button. This will restore everything that EZCA changed in aircraft.cfg files. After that you can safely uninstall EZCA.

7. If you have Track-IR, you should change some settings in the Track-IR software to make it work with EZCA
 - 7.1 Start TrackIR software and update the list of supported games: open the dropdown menu **Games update** and select **Update**.
 - 7.2 After successful update restart TrackIR software.
 - 7.3 Go to the folder where the TrackIR software is installed (typically it's in Program files\NaturalPoints) and rename two files: simconnect.manifest and simconnectSP2.manifest. You can just add some symbol to the end of the name.
 - 7.4 Start TrackIR software and uncheck Trueview checkbox on the **Profile** tab.
 - 7.5 Open Track-IR settings in EZCA and check **Transform XYZ** checkbox.

7. INTERFACE

Important: EZCA is available in the FSX Addons menu. You **MUST BE IN WINDOWED** mode or else you will not see the interface. Windowed mode also allows rapid testing of your settings.



1. Virtual cockpit cameras list.
2. External aircraft cameras list.
3. World cameras list.
4. Joystick button assigned for switching to selected camera.
5. Keyboard shortcut assigned for switching to selected camera.
6. Aircraft type (L – light, M – medium, H – heavy) indication.
7. Camera position limiter button.
8. Effects selection buttons.
9. Indicates that TrackIR is connected to EZCA.

10. Indicates that EZCA is enabled.
11. Indicates that connection with FSX is established.
12. Selected aircraft name.
13. View mode selection buttons.
14. Arrangement buttons.

Cameras lists

These lists display custom cameras created by the user with EZCA.

Cameras created with other addons are not listed and cannot be managed by EZCA. There are three types of cameras.

Note that EZCA is supplied with preset cameras and effects for the default FSX aircrafts only. For your addon aircrafts you will have to create cameras yourself.

Types of the cameras:

Virtual cockpit camera

Cameras related to the virtual cockpit of the aircraft.

Aircraft camera

Cameras related to aircraft external model. They are attached to the aircraft and follow it in flight. Some aircraft's external models have a very detailed visual cabin model. You can place external cameras inside the cabin and get a picture that cannot usually be set up with FSX's own Virtual Cockpit camera. For example, if the external model has a pilot inside the virtual cockpit, you can create an Aircraft camera, place it inside the cockpit, and get a view from within the cockpit that shows the pilot up close.

World camera

Cameras bound to scenery and not to the aircraft. With these cameras you can observe the flight of the aircraft from the ground or from any other point of view, or just walk around. World cameras can be used to create floating camera effects or to walk around the FSX world.

Keyboard shortcuts

You can assign keyboard shortcuts or joystick buttons for switching between cameras. By default there are no assignments. You have to set up them yourself.

Aircraft type

Visual effects of turbulence and vibrations in EZCA depend on the weight of the aircraft. All the aircrafts are divided onto three types. The type of the aircraft is displayed in the “Type” window of the EZCA main window:

L (Light) - less than 4000 Kg.

M (Medium) – 4000 to 50.000 Kg.

H (Heavy) – over 50.000 Kg.

Aircraft name

The Aircraft Name displays the name of the aircraft as it’s specified in the aircraft.cfg file. EZCA uses it to form individual lists of cameras for every aircraft. So if the aircraft.cfg lacks the aircraft name, EZCA will not be able to form a list for it. This case is actually very rare, but if you experience this problem you can manually add it by opening the aircraft.cfg file with any text editor and add it in a value... e.g. `ATC_ID=”aircraft name”`.

Camera position limiter

When enabled this function prevents the camera to go beyond the borders of the cockpit.

Cameras list arrangement buttons.

With these buttons you can rearrange the order of cameras in cameras lists.

8. CAMERA SHAKING MODES

Effects selection buttons.

Clicking these buttons can turn on and off different components of the Camera Shaking effects. EZCA saves the state of the buttons for every camera when making the selection.



RND (Random)

Visual effect simulating the roughness of the surface when the plane is on the ground, and slight general turbulence effect that occur whenever the aircraft is airborne. This is a visual only effect that doesn't take into account the current weather settings of the FSX. This effect depends on the weight of the aircraft and the type of the surface.

DHM (Dynamic head movements)

Simulates the movement of the pilot's head caused by aircraft accelerations during maneuvers, touchdowns, or because of turbulence. Contrary to RND, this effect depends on weather settings. This effect is designed to be used with Virtual Cockpit cameras only.

CR (Camera Resonance)

This effect is similar to Dynamic Head Movement, and simulates the shaking of the camera attached to aircraft parts at touchdown.

Effects can be tuned, their settings imported and exported. See chapter 22 and **Advanced Effects Manual** for detailed information.

9. VIEW MODES CONTROL



There are six buttons that enable or disable different camera modes. EZCA saves the state of the buttons for every camera independently.

PTP (Point-to-Point)

This mode enables or disables smooth switching between the cameras. In this mode camera smoothly floats from the current position to a new one. This effect is only possible if PtP mode is enabled for both cameras: the currently active camera, and the camera you want to switch to. If at least one of the pair has this mode disabled, switching to the camera will occur instantly without the smooth effect.

360° view

This mode enables unlimited camera rotation around the vertical axis (heading). If it's disabled you will not be able to rotate the camera more than 180°.

POV (Point Of View)

This mode allows you to move the camera with the arrow buttons on the keyboard maintaining constant angular positions of the direction of sight. This mode can also be temporarily enabled by pressing and holding middle mouse button.

ML (Mouse Look)

This mode allows the user to look round with the mouse. This mode can also be temporarily enabled by pressing and holding middle mouse button.

Z (Zoom)

Enables camera zoom control with the mouse wheel.

TIR (TrackIR) enables/disables TrackIR view control for particular camera.

10. ADDON STATUS INDICATORS



Indicator **CONNECTED** glows with yellow light indicating that EZCA successfully established connection with the Flight Simulator.

ACTIVE indicates that EZCA is enabled. You can enable and disable EZCA by pressing 3 on numeric keypad or clicking **Global Disable** in the Ezdok section of the **Addons** menu of FSX.




Disabled, EZCA doesn't interfere with other view control systems and doesn't consume CPU resources.

TR indicates that connection with TrackIR is successfully established.

11. GENERAL SETTINGS

To open General Settings window, click **General settings** on the **Options** menu.



1. Mouse look sensitivity and smoothing
2. Keyboard sensitivity and smoothing
3. Presets for Virtual cockpit, Aircraft, and World cameras
4. Click volume settings
5. Mouse and keyboard control settings (disable when the FSX window does not have focus)
6. Disables EZCA when Flight Simulator is in SLEW mode.

7. Self explanatory
8. Shows EZCA icon in Windows Tray.
9. Self explanatory
10. Joystick HAT-switch sensitivity

Keyboard sensitivity and smoothing

You can set camera motion speed by rotating the SPEED knob. Smoothing is adjusted with the SMOOTH knob. Increasing this parameter adds more inertia to the camera. It can be used to simulate a camera crane, or for floating camera effects (look at **Presets**).

Accelerat.1

This knob sets the camera speed increment value in Acceleration mode. You can use this mode to increase the speed of the camera for a short time. It is enabled while you hold the ACC1 button. World cameras have two acceleration buttons; ACC1 and ACC2, with different speed increment value settings. ACC2 can be used for faster moving the camera over long distances.

Mouse look sensitivity and smoothing

This principle is the same as for **Keyboard sensitivity and smoothing settings** above.


Switching Camera confirmation sound

When enabled this will generate a beep sound each time you press the middle mouse button or switch between the cameras. You can adjust the volume of the sound by rotating the knob, or you can simply turn off the sound by moving the slider all the way to the left.

Disable middle mouse button control in EZCA.

Some 3rd party addons use middle mouse button. To avoid conflicts with these addons, disable the use of middle mouse button in EZCA. You can use joystick button or keyboard shortcut instead. See chapter 15 for the details.

12. TRACKIR SETTINGS



1. Self-explanatory.
2. Substitute for Trueview option in the TrackIR software.
3. When checked, EZCA centers the view if TrackClip LEDs or reflective dots are out of TrackIR's sight. The knob sets the delay of centering the view.
- 4 and 5. With these knobs you can set additional smooth for POV movement along the corresponding axes.

13. GETTING STARTED


1. Start FSX. The addon is active right after the FSX is started, but its window is minimized. Switch FSX to windowed mode (you can do this by pressing ALT + ENTER).
2. Open the main addon window by clicking the menu item Addons-> EZdok camera addon -> Show studio:



The EZCA main window will pop up. You can also do it with the keyboard shortcut (SHIFT-D). The main EZCA window looks as follows:



3. Select Joystick Configuration from the Options menu. Select the joystick controllers you would like to use with EZCA.




There are **HAT-switch as button** check boxes to the right of the controllers list. Check them if you would like to use the HAT switch as set of buttons (for switching between the cameras). In the box on the right you can assign a joystick button to toggle between the two modes. If your joystick is in panoraming mode (the checkbox is unchecked), press and hold the assigned button and you will be able to switch between cameras with the HAT-switch. Release the button and the joystick will switch back to panoraming mode.

Note: You should first assign the HAT switch to corresponding cameras. See the following chapters to learn how to do it.


14. SWITCHING BETWEEN THE CAMERAS.

To switch to another camera click the name of the camera you want to switch to on the list. If both current and selected cameras have PtP mode enabled the camera will smoothly float to a position of the selected camera. If any of the cameras have PtP mode disabled, the camera will instantly appear in a new position. You can also switch between the cameras with joystick buttons and/or a keyboard shortcut.



15. ASSIGNING KEYBOARD SHORTCUTS AND JOYSTICK BUTTONS FOR CAMERA SWITCHING.


Click the name of the camera you want to set an assignment to. If you want to assign a keyboard shortcut click “Keyb” box on the main window and enter the keyboard shortcut you want to assign to this camera.



To assign joystick buttons, follow the same principle with the “Joystick” entry field. Note, that if you want to assign a HAT-switch, you should first switch your joystick to **HAT-switch as button** mode as described in chapter 12.



Some EZCA functions are controlled with keyboard shortcuts or joystick buttons only. To set or change assignments click the **Options** menu and then select **Define keys** to open **Keyboard assignment** window.



Forward/Backward/Left/Right/Up/Down - camera movement directions.

Acceleraton1, 2 – camera acceleration buttons

Global enable – enables/disables EZCA

Edit mode – toggles camera Edit mode

Emulate MM button – emulates the middle mouse button with either a joystick button or a keyboard key to switch on and off Mouse look. It has two modes: H - hold and T - toggle. Hold means that Mouse Look is enabled as long as you hold the key or joystick button. Toggle means that you shortly press the button to either enable, or disable Mouse Look.


Default View System – EZCA substitute for default view system. Do not forget to delete the same assignments in the Flight Simulator controllers setup. See chapter 6 for the details.

16. CREATING, DELETING, AND RENAMING VIRTUAL COCKPIT AND AIRCRAFT CAMERAS.

Note: You create cameras before positioning them in chapter 16 below.

There are three ways of creating new cameras: creating “from scratch”, importing from an external file and cloning.

To create a new camera “from scratch”, click three times an empty field on the camera list and enter the name of the camera with the keyboard. Press ENTER. Your new camera is now created.



Creating cameras from scratch can be time consuming, but you can save your time with **cloning** method by using one of the existing cameras as a draft with all its settings. Select the camera you want to clone, and right-click it. Choose **Clone camera with the effects** from the pop-up menu, and the cloned camera will be added to the end of the cameras list. Now you can adjust its position and effects as you need.

Importing camera is similar to cloning, but unlike cloning, where you can deal with only one camera of the current aircraft, with import it is possible to import cameras from another aircrafts: either single camera or the whole set of cameras. See chapter 20 for the details.

To delete a camera, select it with the mouse, right-click, and select **Delete** from the pop-up menu.



To rename a camera, click its name three times and enter new name. Press ENTER. You can change the order of cameras in cameras lists with arrow buttons on the main EZCA window. Select the camera, and use arrows to move the camera up or down on the list.

17. CREATING, DELETING AND RENAMING WORLD CAMERAS

To create a new world camera click an empty field in the World cameras list, and right-click it.



Select “Add camera at aircraft position“ from the pop-up menu. A new world camera will be created from the current aircraft coordinates in FSX. You can use SLEW mode in Flight Simulator to place the camera anywhere you want. World cameras can be deleted the same way as Virtual Cockpit and Aircraft cameras.

Note that you can not rename a world camera. This is a restriction of FSX. To get the same result as rename, you need to delete the camera and after that create the new one with the new name.

18. POSITIONING CAMERAS

Positioning Virtual Cockpit and Aircraft cameras.


To change the position of the camera, switch to this camera and toggle EDIT mode (press button 2 on the numeric keypad by default). You will hear beeps indicating that EZCA is in EDIT mode. Adjust the camera position by using the arrow keys, and set camera elevation with the Page Up and Page Down keys (the name will vary based on your keyboard). Then set the view direction with the mouse, adjusting the camera zoom with the mouse wheel. You then leave EDIT mode by pressing button 2 again on numeric keypad. The stop of the beep sound will indicate that EDIT mode is off.

Positioning World cameras.

You can adjust world camera positions the same way. But this new position can not be saved and exists only during the current flight simulator session. After restart of FSX world cameras will revert back to their default positions. Properties of the world cameras can only be changed manually by editing the FSX cameras.cfg file. We hope this issue will be addressed in the next versions of EZCA.

19. CAMERA POSITION LIMITER

Camera position limiter is a tool that prevents the point of view to go beyond the cockpit limits. The limiter must be tuned before using. Right click the camera position limiter button on the main EZCA window to open the limiter settings.



Hatched areas indicate linear limits of POV movement along the corresponding axes (x, y, z).

Red line shows the current position of the camera.

Ruler below the area is a scale that shows position of the camera and the limits of its movement relative to the cockpit reference point, i.e. default pilot position.

To set appropriate limits of camera movement, drag left and right borders with the mouse. When you drag the border, camera in virtual cockpit simultaneously moves so you will see when to stop and set the limit.

Limiter can be enabled for different axes independently. For example, you want to prevent the camera to go through the instrument panel and ceiling, but you want to be able to look out of the window. So leave axis X unchecked and check axes Y and Z.

20. CAMERA EXPORT AND IMPORT

20.1 Export

You can export cameras to external files to use them as a draft for easy creation of cameras for your addon aircrafts or for sharing with other users.

It is possible to export either single camera, or the whole set of cameras of current aircraft.

- To export only one camera: switch to this camera, select **Export current camera..** from the **File** menu on the main EZCA window and specify folder and file name where to save it.
- To export the whole set of cameras: select **Save camera set..** from the **File** menu on the main EZCA window and specify folder and file name where to save it.

20.2 Import

- To import single camera form external file, select **Import camera to current list** from the **File menu** on the main EZCA window and specify file name of that camera. Your cameras list will be appended with new camera.
- To import set of cameras follow the same principle: select **Load camera set** from the **File menu** on the main EZCA window.

A new window will appear asking you what to load from the file:




Uncheck components you don't want to load (or leave it checked, if you want to load everything) and click **Continue** and specify file name of that set.

21. VIEW MODES SETTINGS


PtP movement speed

You can adjust the camera movement speed in PtP mode. Right-click **PtP** on the main window to open the PtP settings window and adjust Transition time by rotating the knob. Transition time is a duration of the time interval in seconds of camera movement from the current position to a new one. The less its value the faster camera moves.



3D panoraming mode settings

3D panoraming mode combines camera rotation with linear shift. For example: you rotate the camera to the left and while rotating, the camera moves closer to the left window. To open 3D panoraming settings, right-click **ML** on the main window.




There are two knobs that set camera shifts along the axes X and Y. The Value of the shift can be positive and negative. If positive, the camera moves towards the rotation direction, and if negative, the camera moves away.

22. CAMERA SHAKE EFFECTS SETTINGS

22.1 Brief description of RANDOM EFFECT settings.

To open the **Random Effect Settings** window, right-click **RND** on the main window.



1. Main effect generators
2. Profile editor button
3. Active profile indication
4. Mixer-distributor
5. Global gain
6. Filters

Main effect generators

This generator synthesizes composite waveforms. Click the generator's icon to open its settings window. With three independent generators A, B, C you can create different effects like shaking hands while holding the camera, explosions, and crash landings. Please check the support forum for more discussion regarding effect generators.

Profile editor button

The **RND** effect has two independent profiles – **On Ground** and **On air**. When the aircraft is on the ground, EZCA uses the **On Ground** profile to create camera shake caused by surface roughness. When the aircraft becomes airborne, EZCA loads the **On Air** profile that simulates the visual effects created by turbulence. Click the **Profile edit button** to modify profile settings.

Active profile indication

Indicates the selected profile you are editing.


Mixer-distributor mixes signals of the A, B, C generators and distributes them to all degrees and locations of the camera: **deltaX, deltaY, deltaZ, heading, bank, pitch**. This gives you full freedom with your camera views. Since you can set the individual mix of signals for every degree of freedom, it makes it possible to create a large variety of effects in EZCA.

Global Gain

Sets global effect strength.

Dependency processor

With this tool you can set up dependencies between the aircraft speed and the camera shake frequency and amplitude. For example, to simulate camera shake during the take off run we need to have amplitude and frequency increasing with the speed of the aircraft. We can do it by adjusting a curve on the graph by moving the green circles.



Profile editing

To edit the profile, pause Flight Simulator, click **Edit** on the RND effect settings window, and then click **On Ground** or **On Air** to select the profile you want to edit.




EZCA will load the corresponding profile and enable the controls. After you've adjusted the settings, click **Edit** once again to save the settings of the profile and to exit Edit mode.

It is recommended that you backup your current settings before you manipulate the controls so you can restore them later if the new settings will not suit you. To backup your settings, choose from the **File** menu the settings you want to save and when the dialog box appears, specify the folder and file name where you want to save them.

22.2 Brief description of DHM effect settings


Right-click **DHM** on the main window to open **Dynamic Head Movements effects** settings.



- 1, 2, and 3 - Axes input mixers for head movement calculations
- 4. Global effect strength (Main Level)
- 5. Landing effect settings
- 6. Pilot's body parameters.

Note. All the settings, except the Main Level, are the same for all virtual cockpit cameras of the aircraft. Main Level can be set independently for every camera. All the settings are automatically saved to the database after changing. So it is recommended to backup your current settings before you experiment with them.

22.3 Brief description of CAMERA RESONANCE effect settings



Right-click **CR** on the main window to open the Camera Resonance effect settings.

Attack – sets how fast shaking amplitude reaches maximum.

Release – sets how fast shaking amplitude fades to zero.

Frequency – natural-vibration frequency of the camera suspension system.

Level – effect strength level.

23. VIDEO EXAMPLES ON YOUTUBE.COM

[VIDEO 1](#) – EZCA general presentation.

[VIDEO 2](#) – EZCA general presentation.

[VIDEO 3](#) – “Before and after”. Compare the flight with and without EZCA.

[VIDEO 4](#) – RND effect example.

[VIDEO 5](#) – DHM effect example.

[VIDEO 6](#) – CR effect example.

[VIDEO 7](#) – Combination of RND,DHM and CR effects.

[VIDEO 8](#) – Demo flight in severe turbulence.

[VIDEO 9](#) – Hard touchdown.

[VIDEO 10](#) – 3D-panoraming.

[VIDEO 11](#) – Traveling over virtual cockpit with EZCA.

[VIDEO 12](#) – Another views with EZCA .

[VIDEO 13](#) - Hard landing.

Promo video examples created with EZCA.

[VIDEO 14](#) – Example 1.

[VIDEO 15](#) – Example 2.

[VIDEO 16](#) – Example 3.

[VIDEO 17](#) – Example 4.